



## **Linaro Forge Licence Server**

*Release 23.1.1*

**Linaro Limited**

Jan 23, 2024

Copyright © 2023-2024 Linaro Limited. All rights reserved.  
Copyright © 2017-2023 Arm Limited (or its affiliates). All rights reserved.  
Copyright © 2002-2017 Allinea Software Limited.

## CONTENTS

<b>1</b>	<b>Introduction to Linaro Forge Licence Server</b>	<b>1</b>
1.1	Linaro Forge Licence Server . . . . .	1
<b>2</b>	<b>Installation</b>	<b>3</b>
2.1	Install Linaro Forge Licence Server . . . . .	3
<b>3</b>	<b>Use Linaro Forge Licence Server</b>	<b>5</b>
3.1	Run Linaro Forge Licence Server . . . . .	5
3.2	Enable logging . . . . .	6
3.3	Add a new license . . . . .	7
3.4	Licensing example . . . . .	8
3.5	Run product clients . . . . .	9
3.6	Architecture licensing . . . . .	10
3.7	Access Linaro Forge Licence Server behind a firewall . . . . .	11
3.8	Query status . . . . .	11
3.9	Handle lost clients . . . . .	12
3.10	Troubleshoot Licenses . . . . .	13
<b>4</b>	<b>Proprietary notice</b>	<b>15</b>
	<b>Index</b>	<b>17</b>



## INTRODUCTION TO LINARO FORGE LICENCE SERVER

This section describes when you need to use Linaro Forge Licence Server.

### 1.1 Linaro Forge Licence Server

Linaro Forge Licence Server provides licensing support for [Linaro Forge](#).

There are three licensing models for Linaro Forge products:

- Evaluation (Trial) licenses
- Workstation (Node-locked) licenses
- Supercomputing (Floating) licenses

For evaluation and workstation licenses, copy the license file to the Linaro Forge installation directory, {installation-directory}/licences. Linaro Forge Licence Server is not required for these license types.

For supercomputing licenses, Linaro Forge Licence Server is required.

---

**Note:** If you use a remote client, the license is configured on the remote system. A local license is not required.

---

Installation of licenses is discussed further in [Add a new license](#).

When you have determined that Linaro Forge Licence Server is a requirement for your site, you can proceed with [Install Linaro Forge Licence Server](#).

#### 1.1.1 Supported platforms

Linaro Forge Licence Server supports the same **Linux** platforms that Linaro Forge supports. Linaro Forge Licence Server is not supported on Mac or Windows. See [Forge Supported Platforms](#) for more details.

### 1.1.2 Obtaining help

Contact [Forge Support](#).

## INSTALLATION

This chapter describes how to install Linaro Forge Licence Server.

### 2.1 Install Linaro Forge Licence Server

Install remotely using the `textinstall.sh` text-mode install script.

#### 2.1.1 Before you begin

Linaro Forge Licence Server is only available for Linux systems.

#### 2.1.2 Procedure

1. Download a release of Linaro Forge Licence Server from the [Linaro Forge Licence Server Downloads](#).
2. Run the `textinstall.sh` install script provided by using these commands:

```
tar xf linaro-licence-server-<version>-linux-<arch>.tar
```

```
cd linaro-licence-server-<version>-linux-<arch>
```

```
./textinstall.sh
```

- Replace `<version>` with the four digit version number of your installation package using the format `xx.x` for major product releases, and the format `xx.x.x` for support releases.
  - Replace `<arch>` with the required architecture (`aarch64`, `x86_64`, `ppc64le`).
3. When you are prompted, press **Return** to read the license, and enter the path of the installation directory.

---

**Note:** Alternatively, run the text-mode install script `textinstall.sh`, accept the license, and point to an installation directory in one step. You can do this when you execute `textinstall.sh` using `--accept-licence` and `<installation-directory>`.

For example:

```
./textinstall.sh --accept-licence <installation_directory>
```

Replace `<installation_directory>` with your preferred directory.

---

### 2.1.3 Next steps

- See *Use Linaro Forge Licence Server* for details about using Linaro Forge Licence Server.
- See the RELEASE-NOTES file in the install package when the installation is complete.



## USE LINARO FORGE LICENCE SERVER

Linaro Forge Licence Server is required only for floating licenses on HPC clusters. Linaro Forge Licence Server is not required for single evaluation licenses, or workstation licenses (Linaro Forge).

### 3.1 Run Linaro Forge Licence Server

This section describes the process for setting up the Linaro Forge Licence Server and configuring it to start automatically during system boot.

#### 3.1.1 Before you begin

- For security reasons, ensure that Linaro Forge Licence Server runs as an unprivileged user. For example, nobody, or preferably a dedicated user. Furthermore, Linaro recommends restricting the visibility of the host running the Linaro Forge Licence Server only to trusted users, and hidden externally.
- Linaro Forge Licence Server includes a systemd init configuration file for Linux systems.
- If Linaro Forge Licence Server runs without arguments, it uses licenses in the current directory (files matching Licence\* or the variant spelling License\*). You can include an optional argument to specify an alternative directory location instead of the current directory.
- Floating license server files are stored by default in the Linaro Forge Licence Server installation directory (/opt/linaro/licenceserver/<version>/licences). This is also the directory the systemd unit configuration uses by default.

#### 3.1.2 Procedure

1. To create an unprivileged user and allocate a log directory, run these commands as root.

```
useradd --system --user-group --no-create-home \  
    --home-dir /opt/linaro/licenceserver/<version> allinea  
mkdir /var/log/linaro  
chown allinea: /var/log/linaro
```

This creates the user allinea and the log directory /var/log/linaro. The user is assigned ownership of the log directory. The /opt/linaro/licenceserver/<version> directory is the location of the Linaro Forge Licence Server installation. The license server log file is /var/log/linaro/allinea.log.

**Note:** If you install the Linaro Forge Licence Server in a custom installation path, set the `FORGE_LICENSE_DIR` environment variable to point to the custom license directory. `ALLINEA_LICENSE_DIR` is still supported and can be used instead of `FORGE_LICENSE_DIR`.

**Caution:** Ensure that the directory `/var/log` has appropriate access controls to limit access to the log files.

2. Edit `lib/systemd/system/allinea-licenceserver.service` in your Linaro Forge Licence Server installation. Make sure that the `Environment`, `ExecStart` and `User` settings in the `[Service]` section are correct for your system.
3. Create a symbolic link to the `systemd` directory:

```
ln -s lib/systemd/system/allinea-licenceserver.service \
    /etc/systemd/system/
```

4. Enable Linaro Forge Licence Server on future boots:

```
systemctl enable allinea-licenceserver
```

5. Start the Linaro Forge Licence Server:

```
systemctl start allinea-licenceserver
```

6. Check that the Linaro Forge Licence Server has started correctly:

```
systemctl status allinea-licenceserver
```

## 3.2 Enable logging

This section shows you how to enable logging. These steps must be done prior to starting the server.

### 3.2.1 Procedure

1. Set the environment variable `FORGE_LICENSE_LOGFILE` to the file that you wish to append log information to.
2. Set `FORGE_LICENSE_LOGLEVEL` to specify the amount of information required.

The following list specifies the available log levels:

- Level 0: no logging.
- Level 1: client licenses issued are shown, served licenses are listed.
- Level 2: stale licenses are shown when removed, licenses still being served are listed if there is no spare license.
- Level 3: full request strings received are displayed.
- Level 6: is the maximum.

**Caution:** In level 1 and above, the MAC address, user name, process ID, and IP address of the clients are logged. If you need to limit access to the log files, ensure that the directory of the file has appropriate access controls.

## 3.3 Add a new license

This section shows you how to set up a floating license on Linaro Forge Licence Server.

### 3.3.1 Before you begin

- A floating license consists of two files: Server license (Licence.xxxx), and Client license (Licence).
- Server license file names must begin with License, or the variant spelling Licence.
- License file names are not case-sensitive.
- You can append unique identifiers to license file names for storing them in the same directory.

For example, add the server license serial number, `license.server.1234`, or include `client` in the client license name, `license.client.5678`.

### 3.3.2 Procedure

1. Copy the server license file to the `licences` subdirectory of the Linaro Forge Licence Server installation.

For example:

```
/opt/linaro/licenceserver/<version>/licences
```

2. Copy the client license file to the `licences` subdirectory of the licensed product installation, `<product-installation>/<version>/licences`.

For example:

```
/opt/linaro/<product>/<version>/licences/Licence
```

3. Edit the client license file to specify the hostname of the license server in use.
4. Restart Linaro Forge Licence Server for the new floating license to be picked up. Existing clients should not experience disruption if the restart completes promptly.

Multiple floating licenses can be served from the same `licences` directory. If you have multiple licenses for the same product, the license with the most tokens is preferred.

---

**Note:** Linaro Forge Licence Server is required only for floating licenses on HPC clusters. Linaro Forge Licence Server is not required for single evaluation licenses or workstation licenses (Linaro Forge). Copy these license files directly to the `licences` subdirectory in the product installation path, such as, `/home/user/linaro/forge/<version>/licences/Licence.client.5678`.

---

## 3.4 Licensing example

This section shows an example of how the Linaro Forge Licence Server is set up with details of the license file content.

For detailed instructions about how to set up the Linaro Forge Licence Server, see [Run Linaro Forge Licence Server](#).

In this example, a dedicated Linux server machine is running the Linaro Forge Licence Server. It is installed in `/opt/linaro/licenceserver/<version>` and the server license files are stored in `/opt/linaro/licenceserver/<version>/licences`.

The Linaro Forge Licence Server program runs as the dedicated `allinea` user, and serves all licenses in `/opt/linaro/licenceserver/<version>/licences`. Linaro Forge Licence Server logs events to the `/var/log/linaro/allinea.log`.

These commands were run to set up the Linaro Forge Licence Server to:

- create the `allinea` user.
- specify the location of licenses and logs.
- link to the `systemd` init configuration.
- run the Linaro Forge Licence Server and check its status.

```
% useradd --system --user-group --no-create-home \  
    --home-dir /opt/linaro/licenceserver/<version> allinea  
% mkdir /var/log/linaro  
% chown allinea: /var/log/linaro  
% ln -s /opt/linaro/licenceserver/<version>/lib/systemd/system/allinea-licenceserver.service \  
    /etc/systemd/system/  
% systemctl enable allinea-licenceserver  
% systemctl start allinea-licenceserver  
% systemctl status allinea-licenceserver
```

The example server license file is `/opt/linaro/licenceserver/<version>/licences/Licence.server.physics` and is served by `server.physics.acme.edu` on port 4252.

It contains:

```
type=3  
serial_number=1014  
max_processes=48  
expires=2004-04-01 00:00:00  
support_expires=2004-04-01 00:00:00  
mac=00:E0:81:03:6C:DB  
interface=eth0  
debuggers=gdb  
serverport=4252  
max_users=2  
beat=60  
retry_limit=4  
hash2=c18101680ae9f8863266d4aa7544de58562ea858
```

The example client license is stored at `/opt/linaro/forge/<version>/licences/Licence.client.physics`.

It contains:

```
type=2
serial_number=1014
hostname=server.physics.acme.edu
serverport=4252
```

**Note:** The client file `hostname` parameter is manually edited to reference the Linaro Forge Licence Server.

## 3.5 Run product clients

This section describes how to configure the Linaro Forge license files.

### 3.5.1 Before you begin

- A floating license consists of two files: Server license (`Licence.xxx`), and Client license (`Licence`).
- Server license file names must begin with `License`, or the variant spelling `Licence`.
- License file names are not case-sensitive.
- You can append unique identifiers to license file names for storing multiple licenses in the same directory. For example, add the server license serial number, `license.server.1234`, or include client in the client license name, `license.client.5678`.

### 3.5.2 Procedure

1. For each floating license, copy the corresponding client license file to the relevant licences subdirectory in the product installation directory, `<product_installation_directory>/licences`. For example, copy the Linaro Forge client license to `/opt/linaro/forge/<version>/licences`.
2. Edit `hostname` in the client license file to include the hostname or IP address of the machine on which the Linaro Forge Licence Server runs.
3. If your licenses directory is not in the product installation directory, you can specify the directory path to point to the location of the product licenses using the environment variable `FORGE_LICENSE_DIR`.

#### Notes:

- If you include a specific license file name in the `FORGE_LICENSE_DIR` path, the Linaro Forge Licence Server always attempts to serve that specific license.
- You can set the environment variable in a *module* file for the product. For example:

```
export FORGE_LICENSE_DIR=${HOME}/SomeOtherLicenceDir
forge
```

The fields in the client license file are:

Name	Re- quired	Description
hostname	Yes	The hostname, or IP address of the license server
ports	No	A comma separated list of ports to be tried locally for GUI-backend communication. Defaults to 4242,4243,4244,4245
se- rial_number	Yes	The serial number of the server license to be used
serverport	Yes	The port the server listens on
type	Yes	Must have value 2—this indicates that the license requires a server to run correctly

**Note:** The serial number of the server license is specified as this enables a user to be tied to a particular license.

## 3.6 Architecture licensing

Licenses issued after the release of Linaro Forge Licence Server 6.1 specify the compute node architectures that they may be used with. Licences issued prior to this release will enable the x86\_64 architecture by default. Existing users for other architectures will be supplied with new licenses that will enable their architectures.

If there is any problem contact [Forge Support](#).

### 3.6.1 Use multiple architecture licenses

If you are using multiple license files to specify multiple architectures, we recommend that you follow these steps.

#### Procedure

1. Ensure that the default licenses directory is empty.
2. Create a directory for each architecture.
3. To target a specific architecture, set `FORGE_LICENSE_DIR` to the relevant directory. Alternatively, set `FORGE_LICENSE_FILE` to specify the license file.

#### Multiple architectures example

On a site that targets two architectures, x86\_64 and AArch64, create a directory for each architecture, and name them `licenses_x86_64` and `licenses_aarch64`. Then, to target the architectures, set the license directories as follows:

To target AArch64:

```
export FORGE_LICENSE_DIR=/path/to/licenses/licenses_aarch64
```

To target x86\_64:

```
export FORGE_LICENSE_DIR=/path/to/licenses/licenses_x86_64
```

## 3.7 Access Linaro Forge Licence Server behind a firewall

In some scenarios, Linaro Forge Licence Server might be located behind a firewall. This is the case if you are accessing a license server hosted by Linaro. You might also be debugging a system that is not on the same network as the license server. In this case, you can use SSH forwarding to access the license server that is behind the firewall.

A local client license file is created or modified to specify localhost as the hostname parameter:

```
type=2
serial_number=1014
hostname=localhost
serverport=4252
```

Communication is then forwarded over the secure SSH connection to Linaro Forge Licence Server, which listens on port 4252.

This is an example of the command to use for setting up the SSH forwarding:

```
ssh -C -L 4252:server.physics.acme.edu:4242 login.physics.acme.edu
```

The `-C` switch is optional, and enables compression for communication over slow links.

## 3.8 Query status

Linaro Forge Licence Server provides a simple HTML interface to allow for querying of the current state of the licenses being served. This can be accessed in a web browser at the following URL:

```
http://<hostname>:<serverport>/status.html
```

For example, using the values described in [Licensing example](#), the URL would be:

```
http://server.physics.acme.edu:4252/status.html
```

Initially, no licenses are being served, and the output in your browser window would be similar to the following:

```
[Licences start]
  [Licence Serial Number: 1014]
  [No licences allocated - 2 available]
[Licences end]
```

You can see that two licenses are available in this example.

As licenses are served and released, the information displayed will change. To update the status display, simply refresh your web browser window. For example, after one Linaro product is started, the output is updated:

```
[Licences start]
  [Licence Serial Number: 1014]
  [1 licences available]
  [Client 1]
    [mac=00:04:23:99:79:65; uname=gwh; pid=14007; licence=1014]
    [Latest heartbeat: 2004-04-13 11:59:15]
[Licences end]
```

Then, after another Linaro product is started and the web browser window is refreshed (notice the value for number of licences available), the output is updated:

```
[Licences start]
[Licence Serial Number: 1014]
[0 licences available]
[Client 1]
[mac=00:04:23:99:79:65; uname=gwh; pid=14007; licence=1014]
[Latest heartbeat: 2004-04-13 12:04:15]
[Client 2]
[mac=00:40:F4:6C:4A:71; uname=graham; pid=3700; licence=1014]
[Latest heartbeat: 2004-04-13 12:04:59]
[Licences end]
```

Finally, after the first Linaro product finishes:

```
[Licences start]
[Licence Serial Number: 1014]
[1 licences available]
[Client 1]
[mac=00:40:F4:6C:4A:71; uname=graham; pid=3700; licence=1014]
[Latest heartbeat: 2004-04-13 12:07:59]
[Licences end]
```

**Caution:** If you do not want this page to be widely accessible, Linaro recommends authenticating it using a third-party proxy. You can also disable it, before starting the server, by setting the environment variable `FORGE_SILENT_LICENCESERVER=1`.

### 3.9 Handle lost clients

If Linaro Forge Licence Server loses communication with an instance of a client, the license allocated to that client is made unavailable for new clients until a timeout period has expired. The length of this timeout period can be calculated from the license server file values for `beat` and `retry_limit`:

```
lost_client_timeout_period = (beat seconds) * (retry_limit + 1)
```

For the example license files above, the timeout period would be:

```
60 * (4 + 1) = 300 seconds
```

During this timeout period, details of the 'lost' client continue to be output by the status display. As long as additional licenses are available, new clients can be started. However, once all of these additional licenses have been allocated, new clients are refused a license while this timeout period is active.

After this timeout period has expired, the status continues to display details of the 'lost' client until another client is started. Linaro Forge Licence Server grants a license to the new client and the status display then reflects the details of the new client.



## 3.10 Troubleshoot Licenses

Licenses are plain-text which enables you to see the parameters that are set. A checksum verifies the validity of the license.

If problems arise, the first step is to ensure that the parameters specified in the license file are consistent with the machine that is being used (MAC address and IP address), and that the number of users is as expected.

A port which is already used can not be used by Linaro Forge Licence Server. Ensure that you have specified an unused port.

Only privileged users can use ports below 1024, so you should use port 1024 or higher. You should not launch Linaro Forge Licence Server as root due to security issues.



## PROPRIETARY NOTICE

This document is protected by copyright and other related rights and the practice or implementation of the information contained in this document may be protected by one or more patents or pending patent applications. No part of this document may be reproduced in any form by any means without the express prior written permission of Linaro. **No license, express or implied, by estoppel or otherwise to any intellectual property rights is granted by this document unless specifically stated.**

Your access to the information in this document is conditional upon your acceptance that you will not use or permit others to use the information for the purposes of determining whether implementations infringe any third party patents.

THIS DOCUMENT IS PROVIDED AS IS. LINARO PROVIDES NO REPRESENTATIONS AND NO WARRANTIES, EXPRESS, IMPLIED OR STATUTORY, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY, SATISFACTORY QUALITY, NONINFRINGEMENT OR FITNESS FOR A PARTICULAR PURPOSE WITH RESPECT TO THE DOCUMENT. For the avoidance of doubt, Linaro makes no representation with respect to, and has undertaken no analysis to identify or understand the scope and content of, third party patents, copyrights, trade secrets, or other rights.

This document may include technical inaccuracies or typographical errors.

TO THE EXTENT NOT PROHIBITED BY LAW, IN NO EVENT WILL LINARO BE LIABLE FOR ANY DAMAGES, INCLUDING WITHOUT LIMITATION ANY DIRECT, INDIRECT, SPECIAL, INCIDENTAL, PUNITIVE, OR CONSEQUENTIAL DAMAGES, HOWEVER CAUSED AND REGARDLESS OF THE THEORY OF LIABILITY, ARISING OUT OF ANY USE OF THIS DOCUMENT, EVEN IF LINARO HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

This document consists solely of commercial items. You shall be responsible for ensuring that any use, duplication or disclosure of this document complies fully with any relevant export laws and regulations to assure that this document or any portion thereof is not exported, directly or indirectly, in violation of such export laws. Use of the word partner in reference to Linaro's customers is not intended to create or refer to any partnership relationship with any other company. Linaro may make changes to this document at any time and without notice.

If any of the provisions contained in these terms conflict with any of the provisions of any click through or signed written agreement covering this document with Linaro, then the click through or signed written agreement prevails over and supersedes the conflicting provisions of these terms. This document may be translated into other languages for convenience, and you agree that if there is any conflict between the English version of this document and any translation, the terms of the English version of the Agreement shall prevail.

The Linaro corporate logo and words marked with or are registered trademarks or trademarks of Linaro Limited in the US and/or elsewhere. All rights reserved. Other brands and names mentioned in this document may be the trademarks of their respective owners. Please follow Linaro's trademark usage guidelines at <https://www.linaro.org/legal#trademark-usage3>.

Copyright © 2023-2024 Linaro Limited. All rights reserved

Copyright ©2017-2023 Arm Limited (or its affiliates). All rights reserved.

Copyright ©2002-2017 Allinea Software Limited.

Linaro Limited. Company 07180318 registered in England. Harston Mill, Harston, Cambridge, CB22 7GG, UK.

**Confidentiality status**

This document is Non-Confidential. The right to use, copy and disclose this document may be subject to license restrictions in accordance with the terms of the agreement entered into by Linaro and the party that Linaro delivered this document to.

**Product status**

The information in this document is Final, that is for a developed product.

**Web address**

<https://www.linaro.org/>

<https://www.linaroforge.com/>

## INDEX

### O

Obtaining help, [2](#)